System Error Message Selection

This function is used to select and list the Natural system error messages.

Below is an example of how to invoke and execute the function using the Advanced-User mode (see the relevant section):

-

To use the function

- On the "Unload Natural System Error Messages" screen, in the Error Number fields enter a range of numbers or leave the default to select all messages; then, select Select System Error Messages.
- Press ENTER.
 - The List System Error Messages screen appears listing the range of error messages selected.
- If you want to unload one or more objects, select a system error message or specify a range: see Columns and Commands below.
- Press ENTER.
 - The object(s) has been added to the list of unload items.
- Press PF2/Unloa to execute the unload (see also Columns and Commands below).

Columns and Commands

The "List System Error Messages" screen provides the following columns and commands:

Copyright Software AG 2001

Column	PF Key	Explanation		
Cmd		The following line commands can be entered in the input field next to the object desired:		
		L or LI	Lists the error message.	
		S, SE, U or UL	Unload only. Selects the error message for subsequent unloading.	
		DE	Deletes the error message.	
		DL	Deletes the long text of the error message only.	
Number		Lists all Natural system error messages available and provides the option to enter a range of error messages in the input fields of the first row. Valid ranges are:		
		value* All items whose names begin with value.		
		value> All ite	ems whose names are greater than or equal to value. Example: 10>	
		value< All items whose names are less than or equal to value. Example: 100<		
S/L-Kind		Kind of error message text:		
		S Short text of error message.		
		L Long text.		
		A All short and/or long texts.		
Language		Language code(s) of the error messages to be selected:		
		Up to 8 valid Natural language codes. Asterisk (*) selects all language codes.		
	PF2	Unload only.		
Starts unloading the object(s) selected for pro		Starts unloading the	object(s) selected for processing.	
	As an alternative, in the command line, enter either of the following direct commands: UNLOAD			
UNLD				
	DEC	PF6 Moves to the top of the list. PF7 Returns to the previous page. PF8 Goes to the next page. PF9 Moves to bottom of the list. PF11 Selects all objects of the range(s) specified.		
	PF11			
			the command line, enter the following direct command: <u>SEL</u> ECT ALL.	
		2 15 an ancinative, III	and communic fine, enter the following direct collilliand. <u>DEL</u> ECT ALL.	